Educational Laboratory Website Manual

April 30, 2019

Contents

1	Lab I	Information Hub	ţ	
	1.1 I	Introduction		
	1.2 N	Making Changes to Website		
	1	1.2.1 Testing changes before updating live version		
	1	1.2.2 Sync Live Version and Development Space		
2	Experiment Documents 7			
	2.1 I	Introduction		
	2	2.1.1 Criteria for adding document		
	2	2.1.2 Directory structure		
	2.2 A	Adding a new lab to the repository		
		Adding new version of an existing lab		
	2.4 E	Editing Experiment Documents		
		2.4.1 Introduction		
	2	2.4.2 Repository xml template		
3	Equipment 13			
		3.0.1 Inventory structure		
	3	3.0.2 Adding New Equipment		
	-	3.0.3 Adding photos of equipment		
		3.0.4 Deleting Old Equipment		
4	Misc 15			
-		Schedules		
5	Drope	paring Experiment Documents	13	
J	_	Introduction	- •	
		Preparing the Documents		
		Compiling Manuals and PDFs		
		5.3.1 Generating Student PDFs		
6	Safety		19	
U		Orientation		
	0.1	Orientation		
7	Code 21			
		Scripts		

4 CONTENTS

Chapter 1

Lab Information Hub

1.1 Introduction

The purposes of the pjl website is to be the central information hub for the educational physics labs. It is a base of knowledge from which the department can work collaboratively on building the future of education physics labs.

1.2 Making Changes to Website

All changes to the website should be made on the development space on slug (/usr/local/master/pjl-web). The only exception to this rule is that the equipment database equipmentDB.xml can be modified live by using the inventory website in edit mode. Because of this it is important to sync the development and live version of the website before making changes.

1.2.1 Testing changes before updating live version

In the pjl-web folder run the command.

```
python -m SimpleHTTPServer 8000
```

In a browser open up the page localhost:8000. This will show the development version of the website. Confirm that the changes are as expected before updating the live version.

1.2.2 Sync Live Version and Development Space

The script "liveUpdate.py" (Listing 7.1.1) has been designed to sync the live version of the website with the development space for the website. It is important to run this script before and after making changes to the development space. It is run the first time to make sure that the equipment xml file in development has been updated with the changes that made directly on the pjl website. Once the changes to the development space have been made and tested the changes can be pushed to the web-server by running the same command again.

The content displayed by the website is generated from the content of the xml files labDB.xml and equipmentDB.xml WHEEL XML FILES

To sync run...

sudo ./liveUpdate.py

The command can also be run in test mode by executing...

sudo ./liveUpdate.py -t

Chapter 2

Experiment Documents

2.1 Introduction

"Experiment Documents" are a collection of documents used by students in the educational labs, as well as all supporting documents. **ADD SOME EXAMPLES**

2.1.1 Criteria for adding document

Documents can only be added to the repository if they meet the following criteria.

- 1. The files include the pdf given to students to be used in their course work.
- 2. All files need to generate the pdf are included.


2.1.2 Directory structure

At top most level is a folder called "repository" that contains all experiment related documents.

At the second level all the files are organized by lab experiment. Each experiment has a folder that is labeled with a naming scheme where the first four characters are the unique identifier number, followed by the name of the lab. The lab name should be descriptive of the experiment itself. In this folder is also a folder called "Support_Docs" that contains any documents useful for the experiment, but not actually used to generate the student document.

At the third level files are organized into versions. Each folder follows a naming scheme where the the first four characters are the unique lab identifier number, followed by "PHYS" followed by the Course Number followed by a two character semester identifier, followed by the year. Each folder contains all the file used to generate the pdf given to students in the course, semester, and year as identified in the folder label.

Directory structure sample.



2.2 Adding a new lab to the repository

Before beginning ensure that all equipment used in the new experiment are in the lab inventory, and have equipment ID number.

- 1. Create a folder for the new lab (example "new-lab-folder"), and place all files for generating student pdf, and the student pdf in new-lab-folder
- 2. Inside new-lab-folder make a directory called "Support_Docs", and put all documents relevant to lab, but not needed for generation of pdf into it. This might include research papers, sample data, Excel spreadsheets, etc.

```
sudo ./repositoryEdit -n
```

The command can also be run in test mode by executing...

```
sudo ./repositoryEdit -n -t
```

The script will now take you through several steps to gather the information needed to properly add this new lab to the repository. There are several safeties built into the code, but there will be a request to review the input information and confirm that it is correct. Please take time at this point to carefully review metadata entered.

The disciplines, topics, and software entries must align with the master list contained in /data/valid-Diciplines.txt, /data/validTopics.txt, and /data/validSoftware.txt. New items must be added to these master lists before they can be added to a lab.

- Name, Name as to be Seen on Website Use Standard Title Capitalize Convention.
- Type, **Type** Must be either Lab or Labatorial.
- Disciplines, **Discipline1**, **Discipline2** Disciplines must comma separated be taken from the approved list Need location of this list.
- Topics, Topic1, Topic2 Topics must comma separated be taken from the approved list Need location of this list.
- Semester, Semester Winter, Spring, Summer, or Fall
- Year, Year : Four digits.
- Course, Course Number Three digit number corresponding to the course the experiment was used in.
- Equipment, equipID-(Amount)-[alternate equipID], equipID-(Amount) equipID is four digit code of equipment in inventory, Amount is how many are needed, alternate ID is the four digit code of equipment in inventory that can be used if the primary unit is not available. IDs amounts and alternate IDs separated by "-", and items in equipment list separated by ","
- Software, Software1, Software2 Name of all software needed. Must be software from the list of supported software Need location of this list
- PDF, **PDF** exact Name This needs to be the exact name of the student pdf

2.3 Adding new version of an existing lab

Note that a version can only be added once, so make sure that everything outlined below is as desired before proceding to step 4

1. Make a folder that will be contain all file relating to the experiment to add. (ex "0078-PHYS325WI2019" is a suggested name for a folder that would be used to add lab 0078, used in physics 325, for the Winter 2019 semester.)

- 2. Inside the main folder make a folder called "Support_Docs". This folder name is not optional because it will be reference in the scripts used for document and website maintenance.
- 3. In the main folder place. 2.1
 - Main tex file. (ex, Rutherford-Scattering-FULL-WI2019.tex)
 - Student tex file. (ex, Rutherford-Scattering-ST-WI2019.tex)
 - TA guide if it exists. (ex, Rutherford-Scattering-CG-WI2019.tex)
 - PDF of student version of lab. (ex. Rutherford-Scattering-ST-WI2019.pdf)
 - Any file needed to compile the student version of the pdf. (ex, setup-photo.jpg or standard-preamble.tex)
 - Any file that is particular this version of an experiment. (ex template-WI2019.xlsx)
 - Place any general documents into the folder called "Support_Docs". (ex, Interesting-Paper.pdf)
- 4. Run the command.

```
sudo ./repositoryEdit --add
```

Example I/\mathbf{O} from script when adding experiment version.

Enter lab ID number:

0087

Adding version to "Rutherford Scattering"

Enter absolute path for directory containing lab:

/home/pgimby/labs/under-construction/PHYS325WI2019/0078-PHYS300-PHYS0-

Enter the name of the student version pdf:

Rutherford-Scattering-ST-WI2019.pdf

Enter course number:

325

Enter semester:

Winter

Year

2019

Would you like to edit the equipment list for this lab? y/N

 \mathbf{n}

Would you like to edit the software list for this lab? y/N

 \mathbf{n}

Would you like to edit the disciplines list for this lab? y/N

 \mathbf{n}

Would you like to edit the topics list for this lab? y/N

 \mathbf{n}

Is this information correct? N/y:

 \mathbf{y}

Note that the lists of equipment, software, disciplines, and topics can be edited here if desired. For more information on the see **NEED REFERENCE**

5. Sync live version. See section 1.2.2




Figure 2.1: Directory structure and sample contents.

2.4 Editing Experiment Documents

2.4.1 Introduction

All changes should be made to the fill with the word "FULL" in the title. This is one document should contain everything needed to compile the student version and the TA version of an experiment. Different version of a experiment are compiled using the script pjldoc.py **REFERENCE TO HOW TO USE THIS SCRIPT**

2.4.2 Repository xml template

```
<Labs>
    <Lab labId="0001">
        <Name />
        <Disciplines>
            <Discipline />
        </ Disciplines>
        <Topics>
            <Topic />
        </Topics>
        <Versions>
            <Version>
                <Path />
                <Semester />
                <Year />
                <Course />
                <Directory />
            </Version>
        </Versions>
        <Equipment>
            <Item id="0001">
                <Name />
                <Amount />
            </Item>
        <Equipment />
        <Type />
        <SupportDocs>
            <Doc>
                <Name />
                <Path />
            </Doc>
        </SupportDocs>
        <Software>
            <Name />
```



Chapter 3

Equipment

3.0.1 Inventory structure

Each item in the inventory should have a unique identifier number, and a unique name. An item can be either a stand alone item, or a kit. If the item is a kit it will need to include a list of the items the kit. If only part of the kit are needed for an experiment the repository xml can reference those items by creating a equipment tag in the labDB.xml that has the id number for the kit, but the name for the individual item(s). Each item has a place for any number of manuals, and one picture.

All changes outlined in this section are made to the development side of the website. Once all changes have been made, and are satisfactory, the live version of documents must be update and the web server must be updated.

3.0.2 Adding New Equipment

From the /dev/python-tools folder, the command,

```
./equipmentEdit.py -n
```

A prompt will appear that will as for information regarding the new item. Enter all the information available, it is ok leave some fields blank just as long as there is a name. Once all the available information is added a summary will be displayed as well as a request for confirmation. If the user confirms that the information it will go through a validation process to ensure that the name is unique. If everything check out it will be added to the /dev version of the equipmentDB.xml file.

Note: To add Greek letters enter them as (ex. {Omega} or {mu}).

3.0.3 Adding photos of equipment

When taking photos note that they will require editing before they are added to the database. The final version of photo will be square, so keep this in mind when taking the photographs. Note that all images must be in jpg formate.

- 1. Place images in /usr/local/master/labs/rawphotos
- 2. Rename all images using the scheme [idnum]img.jpg where idnum is the id number of the piece of equipment photographed.
- 3. Run the conversion script

```
./convertImg.py
```

4. Enter angle to rotate photos. Photos from some cameras will look like they are properly orientated until they are posted on the website, at which time they will look like they are sideways. It is recommended that when using a new camera that the first image to add is used as a test case to determine if the images need to be rotated by the conversion script.

Edited version will now appear in /usr/local/master/rawimages/output

- 5. Visually check all photographs in the output folder to confirm that they are still acceptable after they have been converted.
- 6. Move all photographs ready to be added to the database to /staffresources/equipment/equiping
- 7. From /dev/python-tools run the script

```
./equipmentEdit.py -i
```

to update the images in the equipmentDB.xml

- 8. Check local version of website, and once the photos are acceptable remove all photos from /usr/local/master/rawimages so that they are not added with the next batch of photos.
- 9. Update live version.

3.0.4 Deleting Old Equipment

To remove a piece of old equipment run, from the python-tools folder, the command,

```
./equipmentEdit.py -d [idnum]
```

If the piece of equipment is currently listed as part of the equipment list for a current lab the script will prompt you to make sure that you know this. Ideally the equipment list in the lab repository should be updated first before removing the equipment. This will help to keep the lab equipment lists and the equipment database in sync.

Chapter 4

Misc

4.1 Schedules

- 1. Create spreadsheet of schedules for the semester. (ex, schedule-WI2019.xlsx)
- 2. Create a PDF of the experiment schedule. (ex, schedule-WI2019.pdf)
- 3. Create a PDF of the lab room schedule. (ex, rooms-WI2019.pdf)
- 4. Place spreadsheet and PDFs in to folder /pjl-web/data/schedules
- 5. Copy /pjl-web/data/schedule-WI2019.pdf to /pjl-web/data/schedule-current.pdf
- 6. Copy /pjl-web/data/rooms-WI2019.pdf to /pjl-web/data/rooms-current.pdf
- 7. Add the previous schedule (ex, schedule-FA2018.pdf) to schedule archive

```
nano /pjl-web/data/schedules/schedule-index.html
```

Paste the code...

...directly before the similar code that exist for the two semesters ago.

8. Add the previous schedule (ex, schedule-FA2018.pdf) to schedule archive

```
nano /pjl-web/data/schedules/room-index.html
```

Paste the code...

16 CHAPTER 4. MISC

...directly before the similar code that exist for the two semesters ago.

Chapter 5

Preparing Experiment Documents

5.1 Introduction

- All tex in one file (lab and companion guide)
- standard preamble file
- pjldoc script for compiling documents
- documents prepared with a root directory of "under-construction"
- document editing timeline

5.2 Preparing the Documents

The following instructions where made specifically for physics 325 in winter 2019. Adjust the names for course and semester.

- 1. Create folder for course named in the form similary to PHYS325WI2019.
- 2. Inside course folder place a sub folder for each lab named in the form 0078-PHYS325WI2019.
- 3. Inside each lab folder there should be...
 - tex file which include student version and companion guide. Name in the form NAME-FULL-WI2019.tex All edits are made to this file
 - Any documents referenced in the tex file which are need for compiling
 - Folder called **Support_Docs** that contain any important documents that are not needed to compile pdfs, such as sample data.
 - File called standard-preamble.tex
- 4. Inside main course folder make a text file called **physics325-lab-order**. Inside this folder list the id numbers of each experiment in the order it should appear in the manual. Be careful not to leave a black line at the end of the file.

5.3 Compiling Manuals and PDFs

All compiling of standard lab documents can be done with the script **pjldoc.py**.

5.3.1 Generating Student PDFs

To compile all of the student PDFs

```
pjldoc.py PHY325WI2019 -s -c -i 0
```

To compile individual PDF of the second lab listed in physics325-lab-order

 $\verb|pjldoc.py| PHY325WI2019 -s -c -i 2|$

Chapter 6

Safety

6.1 Orientation

- Located in /pjl-web/data/safety/lab-safety-manual/
- Edit latest tex file and call it Orientation-WI2019.tex (adjusted for current semester and year)
- \bullet Overwrite file called Orientation.tex with updated version.
- \bullet Compile Orientation.tex
- THERE IS A SYMLINK IN PARENT DIRECTORY. WHICH FILE DOES PJLDOCS LOOK FOR?

Chapter 7

Code

7.1 Scripts

/usr/bin/python3

7.1.1 Add New Lab - addNewLab.py

```
i be called from the command line to make a wide range of changes to the lab repository xml file.
ange include
ding versions of labs from a new semester
ding a brand new lab to repository
port pjlDB
port os, argparse, re
ucntion\ that\ preform\ safety\ checks
f testHost (host):
     Test what computer this being run on. As of now it is machine specific
     Args:
             host\ (str) name of host\ script\ was\ designed\ for
     Return:
             none
     thishost = os.uname()[1]
     if thishost not in host:
             print("This_script_is_designed_to_be_run_on_" + host + "_only._Exiting...")
             exit()
f checkTimeStamp(dev, data):
     Checks that the source files for the databases referenced are the latest. This protects against overwritting change
     Args:
              dev (str) location of a file
             data (str) location of a file
     Return:
```

```
(bool) True if file at data is newer than the one at dev
           , , ,
          if os.path.getmtime(data) <= os.path.getmtime(dev):</pre>
                          return True
          else:
                          return False
unctions used to add a new version entry to the repositorsy xml
'creats a new empty lab object','
f getLabObject(labdb):
          Used to generate a pjl lab object from the labDB.xml database
          Args:
                           labdb (pjlDB.labDB) entire lab database object generated by pjlDB
          Return:
                           lab (pjlDB._LabItem) individual lab item generated by pjlDB
          validID = False
          while not validID:
                          idnum = input("Enter_lab_ID_number:_")
                           if len(idnum) = 4 and idnum.isdigit() = True:
                                           try:
                                                           lab = labdb.getLab(idnum)
                                                           validID = True
                                           except pilDB.IDDoesNotExist: ### not working properly
                                                           print("Message")
                           else:
                                           print ("ID_formate_in_not_valid._Valid_IDs_are_of_the_form_####._Please_try_again")
                                           validID = False
          return lab
'collects information about new version of an existing lab'''
{f f} get {f V}ersion {f Info} (original {f Item} , valid {f C}ourses , valid {f S}emesters , semester {f K}eys , eqdb , discipline {f S}ource , topic {f S}ource , software {f S}ource , t
          Main function that collects information for new version of lab entry
           Args:
                           original I tem\ (pjl DB.\_Lab I tem)\ individual\ lab\ i tem\ generated\ by\ pjl DB
                           validCourses (list) list of valid courses
                           validSemesters (list) list of valid semesters
                           semesterKeys (dict) dictionary that matches semesters with their abreviations
                           eqdb \ (pjlDB.EquipDB) entire equipment inventory database object generated by pjlDB
                           disipline Source\ (str)\ path\ of\ file\ that\ contains\ all\ valid\ disciplines
                           topicSource (str) path of file that contains all valid topics
                           testMode (bool) allows script to be run in testing mode. No output written.
          Return:
                           new_version (dict) dictionary that contains information needed for pjlDB package and a version of a lab to
          print("Adding_version_to_\"" + originalItem.name + "\".")
          new\_version = \{\}
          \#new\_version = \{ \ 'originalDir \ ': \ '/home/pgimby/labs/under-construction/211SP2018/lab2/', \ 'pdf': \ 'Phys \ 211\_221 - Labarana + Labara
          new_version["idnum"] = originalItem.id_num
new_version["name"] = originalItem.name
new_version["type"] = originalItem.lab_type
          new_version["originalDir"] = getOriginalDir()
          print("")
          new_version["pdf"] = getOriginalPdf(new_version["originalDir"])
          new_version["course"] = validCourse(validCourses)
          print("")
```

```
new_version["semester"] = validSemester(validSemesters)
     print(""
     new_version["year"] = validYear()
     new_version ["directory"], new_version ["labFolder"] = validExistingDirectory(new_version, originalItem, semesterKeys)
     new_version["path"] = validPdfPath(new_version)
     new_version["equipment"] = getEquipList(eqdb,originalItem)
     print("")
     new_version["software"] = getSoftwareList(originalItem, softwareSource)
     print("")
     new_version['disciplines'] = getDisciplineList(originalItem, disciplineSource)
     print("")
     new_version['topics'] = getTopicList(originalItem, topicSource)
     return new_version
f getOriginalDir():
     Asks user for location of folder containing new lab, and check that it exists
     Args:
             none
     Return:
             originalDir (str) location of folder containing new lab
     validDir = False
     while not validDir:
             originalDir = input("Enter_absolute_path_for_directory_containing_lab:_")
             if not originalDir.split("/")[-1] == "":
                      originalDir = originalDir + "/"
             print(originalDir)
             if os.path.isdir(originalDir):
                     validDir = True
                     print("Directory_" + originalDir + "_does_not_exist._Please_try_again.")
     return originalDir
f getOriginalPdf(dir):
     Asks user for name of lab pdf file, and check that it exists
     Args:
             dir (str) pathname of the folder that the pdf should be in
     Return:
             pdfName (str) location of pdf file for new lab
     validPath = False
     while not validPath:
             pdfName = input("Enter_the_name_of_the_student_version_pdf:_")
             if os.path.isfile(dir + pdfName):
                     validPath = True
                     print("PDF_does_not_exist._Please_try_again.")
     return pdfName
f validCourse (validCourses):
     Asks user to enter the course the lab was used in, and checks it against a list of valid courses
     Args:
             validCourses (list) list of valid courses
     Return:
             course (str) valid course number
```

```
validCourse = False
     while not validCourse:
             courseNum = str(input("Enter_course_number:_"))
             for i in validCourses:
                     if courseNum == i:
                              course = "PHYS_" + courseNum
                              validCourse = True
             if not validCourse:
                     print("Invalid _Course_number")
                     print("Valid_courses_are...")
                     for i in validCourses:
                             print(i)
     return course
f validSemester (validSemesters):
     Asks user to enter the semester the lab was used in, and checks it against a list of valid semesters
     Args:
             validSemesters (list) list of valid courses
     Return:
             semesterName (str) valid semester name
     validSemester = False
     while not validSemester:
             semesterName = str(input("Enter_semester:_")).capitalize()
             for i in validSemesters:
                      if semesterName == i:
                              validSemester = True
             if not validSemester:
                     print("Invalid_semester")
                     print("Valid_semesters_are...")
                     for i in validSemesters:
                             print(i)
     return semesterName
f validYear():
     Asks user to enter the year the lab was used in, and checks that it is a valid year
     Args:
             none
     Return:
             year (str) valid 4 digit year
     validYear = False
     while not validYear:
             year = input("Enter_year:_")
             if len(year) == 4 and year.isdigit() == True:
                     validYear = True
             else:
                     print("Year_is_invalid.")
     return year
f validExistingDirectory(new_version, lab, semesterKeys):
     Takes information entered from user, and determines the name of the folder that will
     contain version of lab that will be added. This uses knowledge of other version folder
     that have already been added. Will not work for a new Lab (see function versionFolder)
     Args:
             new_version (dict) information entered by user
             lab (pjlDB._LabItem) individual lab item generated by pjlDB
             semesterKeys (dict) matches abreviations for semesters with full name
     Return:
```

```
directory (str) full path name on new version directory
      , , ,
     samplePath = lab.versions[0]["directory"
     labFolder = "/".join(samplePath.split("/")[:-1]) + "/"
     semester = semesterKeys[new_version["semester"]]
     courseNum = new_version["course"].split("_")[-1]
year = new_version["year"]
     directory = labFolder + lab.id_num + "-PHYS" + courseNum + semester + year + "/"
     return directory, labFolder
f validPdfPath (new_version):
     Asks user to input the path to the pdf to display on the webpage for this version
     Arqs:
              new_version (dict) information entered by user
     Return:
              path (str) final path to pdf
     validPath = False
     while not validPath:
              pdfName = new_version["pdf"]
              if os.path.isfile(new_version["originalDir"] + pdfName):
                      validPath = True
                      path = new_version["directory"] + pdfName
              else:
                      print("PDF_does_not_exist._Please_try_again.")
     return path
f getEquipList(eqdb,originalItem):
     generates a list of equipment
     Args:
              eqdb (pjlDB.EquipDB) entire equipment inventory database object generated by pjlDB
              original Item \ (pjlDB.\_Lab Item) \ individual \ lab \ item \ generated \ by \ pjlDB
     Return:
              equipItems (list of dictionaries)
      , , ,
     print("")
     if input("Would_you_like_to_edit_the_equipment_list_for_this_lab?_y/N_").lower() = "y":
              print("'
              print("Current_Equipment_List")
              print ("-
              for i in originalItem.equipment:
                      # i['alt-name'] = "TEST NAME"
# i['alt-id'] = "0000"
                      print(i['id'] + "-" + i['name'] + "-[" + i['alt-id'] + "-" + i['alt-name'] + "]-" + "-(" + i['amour
              equipItems = []
              equipItems = equipInfoReview(eqdb, originalItem)
              allItems = False
              while not allItems:
                      print("")
                       if input("Would_you_like_to_add_a_new_piece_of_equipment_for_this_lab?_y/N_").lower() == "y":
                               itemId = input("Enter_the_equipment_id_number:_")
                               equipItems.append(addEquipItem(eqdb,itemId))
                      else:
                               allItems = True
     else:
              equipItems = originalItem.equipment
     return equipItems
f equipInfoReview (eqdb, originalItem):
     Controls the review and editing of equipment list. Asks user to input id numbers and
```

```
quantity of equipment needed for the new lab. User also can input an alternate/secondary
     equipment item for each primary item
     Input id numbers are check for correctness
     Args:
              eqdb (pjlDB. EquipDB) entire equipment inventory database object generated by pjlDB
              originalItem (pjlDB._LabItem) individual lab item generated by pjlDB
     Return:
              equipItems (list of dictionaries)
      , , ,
     equipItems = []
     if originalItem.equipment:
              for i in originalItem.equipment:
                       print("ID_Number_[" + i['id'] + "]: _Name_[" + i['name'] + "]: _Alternate_Name: _[" + i['alt-name'] +
if input ("Would_you_like_to_edit_this_entry?_y/N:_").lower() == "y":
                                equipID = input("Enter_new_id_number_[" + i['id'] + "],_enter_'delete'_to_remove_this_item_
                                if equipID == "":
                                equipID = i['id']
if not equipID == "delete":
                                        item = addEquipItem(eqdb, equipID)
                                        print("enter_editing_code_here")
                                else:
                                        print("deleting_" + i['id'] + "_" + i['name'])
                       else:
                                equipItems.append(i)
     return equipItems
f addEquipItem(eqdb, itemId):
     Adds a new piece of equipment to a lab object
     Args:
              eqdb (pjlDB. EquipDB) entire equipment inventory database object generated by pjlDB
              itemId (str) equipment id number entered by user
     Return:
              equipItem (dict) dicitonary for single equipment item
     equipItem = \{\}
     validItem = False
     validAlt = False
     validNum = False
     itemName = ""
     altName = ""
     \mathrm{amount} \ = \ ""
     \# adds main item
     while not validItem:
              if itemId == "retry":
                       itemId = input("Enter_the_equipment_id_number:_")
              validItem, itemName, itemError = equipValid(eqdb, itemId)
              if not validItem:
                       print(itemError)
                       if input("Do_you_wish_to_try_again?_Y/n:_").lower() == "n":
                               break
                       else:
                               itemId = "retry"
              else:
                       equipItem['id'] = itemId
                       equipItem ['name'] = itemName
                       validItem = True
     \# adds alternate item
     while not validAlt:
              altId = input("Enter_id_number_of_an_alternate_for_this_item._If_none_hit_Enter._")
              if not altId == "":
```

```
validAlt, altName, altError = equipValid(eqdb, altId)
                        if not validAlt:
                                print(altError)
                                 if input("Do_you_wish_to_try_again?_Y/n:_").lower() == "n":
                                         break
                                 else:
                                         altId = ""
                                         altName = ""
                                         validAlt = False
                       else:
                                \begin{array}{lll} equipItem\left[ \; 'alt\,-name \; ' \; \right] \; = \; altName \\ equipItem\left[ \; 'alt\,-id \; ' \; \right] \; = \; altId \end{array}
                                validAlt = True
               else:
                       equipItem['alt-name'] = ""
equipItem['alt-id'] = ""
                        validAlt = True
     # adds the number of units needed
     while not validNum:
              amount = input("Please_enter_how_many_" + itemName + "(s)_are_needed?_")
               if amount.isdigit():
                       equipItem ['amount'] = amount
                       validNum{=}True
              else:
                        print(amount + "_is_not_a_valid_number.")
                        if input("Do_you_wish_to_try_again?_Y/n:_").lower() == "n":
                                break
              equipItem["id"] = itemId
     return equipItem
f equipValid(eqdb,itemID):
      Checks if equipment item added by user for new lab is valid
      Args:
               eqdb (pjlDB.EquipDB) entire equipment inventory database object generated by pjlDB
              itemID (str) Id number of equipment item to add
      Return:
               validItem (bool)
              name (str) Name of equipment item
               errorMessage (str) Information on why a equipment entry is invalid
     errorMessage = ""
      if len(itemID) = 4 and itemID.isdigit() = True:
              \mathbf{try}:
                       item = eqdb.getItem(idnum=itemID)
                       name = item.name
                       errorMessage = ""
                       return True, name, errorMessage
              except pjlDB.EQIDDoesNotExist as e:
                       errorMessage = ("Invalid_Equipment:_Item_" + itemID + "_does_not_exist.")
                       name = "null"
                       return False, name, errorMessage
     else:
              errorMessage = ("Invalid_Equipment:_Id_needs_to_be_a_4_digit_number")
              name = "null"
              return False, name, errorMessage
f getSoftwareList(originalItem, softwareSource):
      generates a list of software
     Args:
               originalItem (pjlDB._LabItem) individual lab item generated by pjlDB
               software Source (string) path to file containing list of available software
```

```
Return:
              softwareItems (list) valid software
     softwareItems = []
      if \ input ("Would_you_like_to_edit_the_software_list_for_this_lab?_y/N_-"). \ lower() == "y": \\
              print("")
              print ("Current_Software")
              print ("-
              for i in originalItem.software:
                      print(i)
              print(""
             softwareItems = []
             softwareItems = softwareRemove(originalItem)
              allItems = False
              while not allItems:
                      if input("Would_you_like_to_add_a_new_software_for_this_lab?_y/N_").lower() == "y":
                              print("")
                              masterList = getValidList(softwareSource)
                              print("")
                              print("Valid_Software")
                              printList ( masterList )
                              softwareItems.append(getNewSoftware(masterList))
                      else:
                              allItems = True
             softwareItems = list(set(softwareItems))
     else:
             softwareItems = originalItem.software
     return softwareItems
f softwareRemove(originalItem):
     Removes unwanted software
     Args:
              originalItem (pjlDB._LabItem) individual lab item generated by pjlDB
     Return:
              softwareItems (list) wanted software
     softwareItems = []
     if originalItem.software:
              for i in originalItem.software:
                      if not input("Would_you_like_to_remove_\"" + i + "\"_as_needed_software?_If_so_enter_'delete':_").l
                              softwareItems.append(i)
     return softwareItems
f getNewSoftware (masterList):
     Get list of software from user and check if they are valid
     Args:
              masterList (list) complete pool of valid topics
     Return:
              software (str) single valid software for new lab
     valid = False
     while not valid:
              item = input("Enter_new_software:_")
              for i in masterList:
                      if i.lower() == item.lower():
                              valid = True
                              item = i
                              print("Adding_" + i + "_to_software")
print("")
              if not valid:
                      print(item + "_is_invalid_software.")
                      if not input("Would_you_like_to_try_again?_{-}Y/n_{-}").lower() == "n":
```

```
continue
                      else:
                              break
     return item
f getValidList(listSource):
     Generates list of valid selections from file
     Arqs:
              listSource (string) path to file containing valid list entries
     Return:
              validList (list) list of valid selections
     validList = open(listSource).readlines()
     for i in range (0,len(validList)):
             validList[i] = validList[i].replace('\n','').strip()
     validList = list(filter(None, validList))
     return validList
f getDisciplineList (originalItem, disciplineSource):
     generates a list of disciplines
     Args:
              originalItem (pjlDB._LabItem) individual lab item generated by pjlDB
              disciplineSource (string) path to file containing list of disciplines
     Return:
              discipline I tems (list) valid disciplines
     disciplineItems = []
     if\ input("Would_you_like_to_edit_the_disciplines_list_for_this_lab?_y/N_-").lower() == "y":
             print("
             print ("Current_Disciplines")
             print ("-
             for i in originalItem.disciplines:
                      print(i)
             print("")
              disciplineItems = []
              disciplineItems = disciplineRemove(originalItem)
              allItems = False
              while not allItems:
                       if \ input("Would_you_like_to_add_a_new_discipline_for_this_lab?_y/N_"). lower() == "y":
                              print("")
                              masterList = getValidList(disciplineSource)
                              print("")
                              print ("Valid_Disciplines")
                              printList ( masterList )
                              disciplineItems.append(getNewDisciplines(masterList))
                      else:
                              allItems = True
              disciplineItems = list(set(disciplineItems))
     else:
              disciplineItems = originalItem.disciplines
     return disciplineItems
f disciplineRemove(originalItem):
     Removes unwanted disciplines
     Args:
              originalItem (pjlDB._LabItem) individual lab item generated by pjlDB
     Return:
              discipline I tems \ (list) \ wanted \ disciplines
```

```
disciplineItems = []
     if originalItem.disciplines:
             for i in originalItem.disciplines:
                      if not input ("Would_you_like_to_remove_\"" + i + "\"_as_a_discipline?_If_so_enter_'delete':_").lowe
                              disciplineItems.append(i)
     return disciplineItems
f getNewDisciplines(masterList):
     Get list of disciplines from user and check if they are valid
     Args:
              masterList (list) complete pool of valid topics
     Return:
              disciplines (str) single valid discipline for new lab
      , , ,
     valid = False
     while not valid:
              item = input("Enter_new_discipline:_")
              for i in masterList:
                      if i.lower() == item.lower():
                              valid = True
                              item = i
                              print("Adding_" + i + "_to_disciplines")
print("")
              if not valid:
                      print(item + "_is_an_invalid_discipline.")
                      if not input("Would_you_like_to_try_again?_Y/n_").lower() == "n":
                              continue
                      else:
                              break
     return item
f getTopicList(originalItem, topicSource):
     generates a list of topics
     Args:
              originalItem (pjlDB._LabItem) individual lab item generated by pjlDB
              topicSource (string) path to file containing list of topics
     Return:
              topicItems (list) valid topics
     topicItems = []
     if input("Would_you_like_to_edit_the_topics_list_for_this_lab?_y/N_").lower() == "y":
             print("")
             print("Current_Topics")
             print("—
             for i in originalItem.topics:
                      print(i)
             print("")
              topicItems = []
              topicItems = topicRemove(originalItem)
             print("")
              allItems = False
              while not allItems:
                      if input("Would_you_like_to_add_a_new_topic_for_this_lab?_y/N_").lower() == "y":
                              print("")
                              masterList = getValidList(topicSource)
                              print("")
                              print("Valid_Topics")
                              printList(masterList)
                              topicItems.append(getNewTopic(topicSource, masterList))
                      else:
                              allItems = True
```

```
topicItems = list(set(topicItems))
      else:
               topicItems = originalItem.topics
      return topicItems
f topicRemove(originalItem):
      Removes unwanted topics
      Args:
               originalItem (pjlDB._LabItem) individual lab item generated by pjlDB
      Return:
               topicItems (list) wanted topics
      topicItems = []
      if originalItem.topics:
               for i in originalItem.topics:
                         if not input("Would_you_like_to_remove_\"" + i + "\"_as_a_topic?_If_so_enter_'delete':_").lower() =
                                  topicItems.append(i)
      return topicItems
f getNewTopic(topicSource, masterList):
      Get list of topics from user and check if they are valid
      Args:
               topicSource (string) path to file containing list of disciplines
               masterList (list) complete pool of valid topics
      Return:
               topics (str) single valid topic
      valid = False
      while not valid:
               item = input("Enter_new_topic:_")
               for i in masterList:
                         if i.replace(",",").lower() = item.replace(",",").lower():
                                  valid = True
                                  item = i
                                  print(item)
                                  print("Adding_" + i + "_to_topics")
                                  print("")
               if not valid:
                         \begin{array}{lll} \textbf{print} (\texttt{item} + \texttt{"\_is\_an\_invalid\_topic."}) \\ \textbf{if} \ \ \textbf{not} \ \ \textbf{input} (\texttt{"Would\_you\_like\_to\_try\_again?\_Y/n\_"}). \ \texttt{lower}() == \texttt{"n"}: \end{array}
                                  continue
                         else:
                                  break
      return item
f printList(lst):
      Prints a list of strings line by line for easy readability
      Args:
               lst (list) list of strings to be printed
      Return:
               none
      print ("-
      for i in lst:
               \mathbf{print}(i)
      print("")
f confirmEntry(new_version):
```

```
print out what information entered by usee, and asks for confirmation
     Args:
              new_version (dict) dictionary containing all data in for that pjlDB can enter into database
     Return:
              (bool) True if information has been confirmed by user
     print("")
     print("Please_confirm_that_the_information_entered_is_correct")
     print("lab_id:_" + new_version["idnum"])
     print("name: _" + new_version["name"])
     print("type: " + new_version["type"])
     print("original_Directory: " + new_version["originalDir"])
     print("course: " + new_version["course"])
print("semester: " + new_version["semester"])
     print("year: " + new_version["year"])
     print("directory: " + new_version["directory"])
     print("path: " + new_version["path"])
print("equipment: ")
     printList(new_version["equipment"])
     print("disciplines:_"
     printList (new_version["disciplines"])
     print("topics:_")
     printList(new_version["topics"])
     if not input ("Is_this_information_correct?_N/y:_").lower() = "y":
              print("exiting...")
              exit()
f validDB (info, lab, labdb):
     adds lab object to database and checks that database is valid
     Args:
              info (dict) information about new lab object
              lab (pjlDB._LabItem) individual lab item generated by pjlDB
              lab\,db (pjlDB.LabDB) entire lab database object generated by pjlDB
     Return:
              (bool) True if labDB object is valid
     lab.id_num = info["idnum"]
     lab.name = info["name"]
     lab.lab_type = info["type"]
lab.equipment = info["equipment"]
     lab.software = info["software"]
     lab.disciplines = info ["disciplines"]
     lab.topics = info["topics"]
     lab.addVersion(info)
     valid = labdb.validateFull()
     if valid:
              return valid
     else:
              return False
unctions for moving directory into repository
f validDir(info, root):
     checks that the verison has not already been added to repository file structure
     Args:
              info (dict) information about new lab object
              root (str) root path of lab repository
     Return:
```

```
(bool) True is lab has not already been added to repository file structure
     versionDir = root + info["directory"]
     if not os.path.isdir(versionDir):
             return True
     else:
              print("Lab_folder_" + versionDir + "_Already_Exists.")
             print("Exiting...")
             return False
f moveVersionDir(info, root):
     adds\ source\ file\ to\ lab\ repository\,.
              Makes new directory
              rsyncs files except for contents of Support_Docs folder
     Args:
              info (dict) information about new lab object
              root (str) root path of lab repository
     Return:
              none
     versionDir = root + info["directory"]
     if not os.path.isdir(versionDir):
             os.system("mkdir_" + versionDir)
             #os.system("echo rsync -avz -- exclude Support_Docs " + info["originalDir"] + " " + versionDir)
             os.system("sudo_rsync_-avz_-exclude_Support_Docs_" + info["originalDir"] + "_" + versionDir)
     else:
             print("Lab_folder_" + versionDir + "_Already_Exists.")
             print ("Exiting ...")
              exit()
unctions for updating Support\_Docs
f addSupportFolder(info, root):
     adds contents of Support_Docs folder to repository
     Args:
              info (dict) information about new lab object
     Return:
              none
      , , ,
     originDir = info["originalDir"] + "Support_Docs"
     destinationDir = root + info["labFolder"] + "Support_Docs"
     if os.path.isdir(originDir):
              if not os.path.isdir(destinationDir):
                      print("Support_Docs_Folder_does_not_exist._Adding_new_folder_" + destinationDir)
                      os.system("mkdir_" + destinationDir)
              if os.path.isdir(destinationDir):
                      os.system("rsync\_-avz\_" + originDir + "/\_" + destinationDir)\\
             else:
                      print("Something_when_wrong._Exiting...")
                      exit()
Functions for adding a new lab
f getNewLabInfo(originalItem, testMode):
     Main function that collects information for new lab entry
     Args:
              original I tem\ (pjl DB.\_Lab I tem)\ individual\ lab\ i tem\ generated\ by\ pjl DB
```

```
validCourses (list) list of valid courses
              validSemesters (list) list of valid semesters
              semesterKeys (dict) dictionary that matches semesters with their abreviations
              eqdb (pjlDB.EquipDB) entire equipment inventory database object generated by pjlDB
              disipline Source (str) path of file that contains all valid disciplines
              topicSource (str) path of file that contains all valid topics
              testMode (bool) allows script to be run in testing mode. No output written.
     Return:
              new_lab (dict) dictionary that contains information needed for pjlDB package to create new lab object
              labFolder (str) path of parent folder to create for new lab
      , , ,
     new_lab = \{\}
     new_versions = []
     new_version = {}
     new_lab["idnum"] = originalItem.id_num
     print("Adding_new_lab_with_id_number:_[" + new_lab["idnum"] + "]")
     print("-
     print("")
     \begin{array}{ll} {\tt new\_lab\,["name"]\ =\ getName\,(\,originalItem\,)} \end{array}
     print("")
     new_lab ["type"] = getType()
     new_lab["originalDir"] = getOriginalDir()
     print("
     new_lab["pdf"] = getOriginalPdf(new_lab["originalDir"])
     print(","
     new_lab["course"] = validCourse(validCourses)
     print("")
     new_lab["semester"] = validSemester(validSemesters)
     print("")
     new_lab["year"] = validYear()
     print("")
     new_version
     new_lab["labFolder"], new_lab["labFolderPath"] = newLabFolder(new_lab)
     print ("-
     print (new_lab ["labFolderPath"])
     print(new_lab["labFolder"])
     new_lab ["directory"] = versionFolder (new_lab, semesterKeys)
     print(new_lab["directory"])
new_lab["path"] = validPdfPath(new_lab)
     new_lab["equipment"] = getEquipList(eqdb,originalItem)
     new_lab["software"] = getSoftwareList(originalItem, softwareSource)
     print(""
     new_lab['disciplines'] = getDisciplineList(originalItem, disciplineSource)
     print("")
     new_lab['topics'] = getTopicList(originalItem, topicSource)
     new_version["path"] = new_lab["path"
new_version["year"] = new_lab["year"
     new_version["semester"] = new_lab["semester"]
     new_version["course"] = new_lab["course"]
     new_version["directory"] = new_lab["directory"]
     new_versions.append(new_version)
     new_lab["versions"] = new_versions
     return new_lab
f getName(originalItem):
     Asks user to enter name of new lab, and check that the name is not already used
     Arqs:
              original I tem\ (pjl DB.\_Lab I tem)\ individual\ lab\ i tem\ generated\ by\ pjl DB
     Return:
              labName (str) name of new lab
     labName = originalItem.name
```

```
if originalItem.name == "":
              validName = False
             while not validName:
                      labName = str(input("Enter_name_of_the_new_lab._Please_use_conventional_titlecase_(ie._This_is_a_T
                      if input("Is_this_name_entered_correctly?_N/y:_").lower() == "y":
                              validName = True
                      elif input("Would_you_like_to_try_again?_Y/n_").lower() == "n":
                              print ("Exiting.")
                              exit()
     return labName
f getType():
     asks user what type of experiment this is. There are only two options lab or labatorial
     Args:
             n.on.e
     Return (str) type experiment. lab or labatorial
     validType = False
     while not validType:
             labType = input("Is_this_a_lab_or_a_labatorial?_").lower()
              if labType = "lab" or labType = "labatorial":
                      validType = True
              else:
                      if input ("Would_you_like_to_try_again?_{Y}/n:_{"}). lower() == "n":
     return labType.capitalize()
f newLabFolder(info):
     determine name of folder for a new lab
     Args:
              info (dict) information about new lab object
     name = "-".join(info["name"].split(""))
     labFolder = "/data/repository/" + info["idnum"] + "-" + name
     labFolderPath = root + labFolder
     return labFolder, labFolderPath
f versionFolder (info, semesterKeys):
     determine name of folder for a new lab. This is different than the function
     (valid Existing Directory)\ which\ uses\ knowledge\ of\ existing\ version\ folders\,.
     Args:
              info\ (dict)\ information\ about\ new\ lab\ object
              labFolder (str) path of the new lab parent folder in repository
              semesterKeys (dict) matches full name semesters with abreviation
     Return:
              directory (str) path of version directory for a new lab
     semester = semesterKeys[info["semester"]]
     courseNum = info["course"].split("")[-1]
     directory = info ["labFolder"] + "/" + info ["idnum"] + "-PHYS" + courseNum + semester + info ["year"] + "/"
     return directory
f validNewLab(info, lab, labdb):
     adds lab object to database and checks that database is valid
     Args:
              info (dict) information about new lab object
              lab\ (pjlDB.\_LabItem)\ individual\ lab\ item\ generated\ by\ pjlDB
```

 $labdb\ (pjlDB.LabDB)\ entire\ lab\ database\ object\ generated\ by\ pjlDB$

```
Return:
              (bool) True if labDB object is valid
     lab.id_num = info["idnum"]
     lab.name = info["name"]
     lab.lab_type = info["type"]
     lab.equipment = info["equipment"]
     lab.software = info["software"]
     lab.disciplines = info["disciplines"]
     lab.topics = info["topics"]
     lab.versions = info["versions"]
     labdb.addLab(lab)
     valid = labdb.validateFull()
     if valid:
             return valid
     else:
              return False
f getEditInfo(originalItem,eqdb,disciplineSource,topicSource,softwareSource,testMode):
     Main function that collects information for new version of lab entry
     Args:
              originalItem (pjlDB._LabItem) individual lab item generated by pjlDB
              eqdb (pjlDB.EquipDB) entire equipment inventory database object generated by pjlDB
              disiplineSource (str) path of file that contains all valid disciplines
              topicSource (str) path of file that contains all valid topics
              testMode (bool) allows script to be run in testing mode. No output written.
     Return:
              originalItem (pjlDB._LabItem) updated individual lab item
     print("Editing_info_for_\"" + originalItem.name + "\".")
     print("")
     originalItem.equipment = getEquipList(eqdb,originalItem)
     print("")
     original Item.\, software \, = \, getSoftwareList \, (\, original Item \, , softwareSource \, )
     print("")
     originalItem.disciplines = getDisciplineList(originalItem, disciplineSource)
     print("")
     originalItem.topics = getTopicList(originalItem, topicSource)
     return originalItem
f displayLabItem(lab):
     print("")
     print("Please_confirm_that_the_information_entered_is_correct.")
     print ("-
     print("lab_id:_" + lab.id_num)
print("")
     print("name: " + lab.name)
     print("")
     print("type:" + lab.lab_type)
     print("")
print("equipment: ")
     print("——")
     printEquipList(lab.equipment)
     print("")
     print (" disciplines : _")
     printList (lab. disciplines)
     print("topics:_")
     printList(lab.topics)
      \textbf{if input} ("Is\_this\_information\_correct?\_N/y:\_"). lower() == "y": \\
              return True
     else:
              print("exiting...")
              return
              exit()
```

```
f printEquipList (equipList):
       for i in equipList:
                   print(i["id"] +": " + i["name"] + " ["amount"] + "), " + i["alt-id"] + ": " + i["alt-name"])
ain Script
rsion = "1.1"
List of valid courses and semesters ',',
LidCourses = ["211", "223", "227", "255", "259", "323", "325", "341", "365", "369", "375", "397", "497"]
LidSemesters = ["Winter", "Spring", "Summer", "Fall"]
nesterKeys = {"Winter": "WI", "Spring": "SP", "Summer": "SU", "Fall": "FA"}
'Define user options','
rser = argparse.ArgumentParser(
       formatter_class=argparse.RawDescriptionHelpFormatter, epilog='''
ow bugs and other important information:
       A) Blank Topics or Discplies was causing issures. I think
       B) \ \ Spaces \ \ in \ \ the \ \ names \ \ of \ \ folders \ \ does \ \ not \ \ work \, .
       C) Review does not include software.
       D) Cannot add additional docs.
')
rser.add_argument('-a', '--add', help='Add_a_new_version_to_an_existing_lab.".', action='store_true')
rser.add_argument('-e', '--edit', help='Edit_the_details_of_a_lab.', action='store_true')
rser.add_argument('-n', '--new', help='Add_a_brand_new_lab.".', action='store_true')
rser.add_argument('-t', '--test', help='Debug_mode.', action='store_true')
rser.add_argument('-x', '--validate', help='Disable_validation_for_xml.', action='store_true')
rser.add_argument('-v', '--version', help='Print_current_verion_of_script.', action='store_true')
gs = parser.parse_args()
tMode = args.test
lidate = args.validate
'Paths for files','
ot = "/usr/local/master/pjl-web"
lbDev = root + "/dev/equipmentDB.xml"
dbDev = root + "/dev/labDB.xml"
lbData = root + "/data/equipmentDB.xml"
dbData = root + "/data/labDB.xml"
sciplineSource = root + "/data/validDisciplines.txt"
picSource = root + "/data/validTopics.txt"
twareSource = root + "/data/validSoftware.txt"
'Changes the output to a temporary file if script is run in test mode'''
testMode:
       destXML = root + "/dev/test_labDB.xml"
                             ---Running_in_test_mode.---
e:
       destXML= labdbDev
'validation disabled warning','
validate:
       print("validation_of_output_file_has_been_disabled._Be_Very_Careful!")
'name of host machine this scipt was written for'''
evhost = "sluq"
whost = ["slug", "fry"]
'Confirm that this script won't accidently run on the wrong machine'''
tHost (devhost)
```

```
'Create pjlDB object of each of the relevent xml files'''
lb = pjlDB . EquipDB (eqdbDev)
db = pjlDB.LabDB(labdbDev)
'prints version','
args.version:
     print("Version" + version)
     exit()
'Checks that the development version of both key DBs are new or as new as the live versions.'''
not checkTimeStamp(eqdbDev,eqdbData) or not checkTimeStamp(labdbDev,labdbData):
     if not checkTimeStamp(eqdbDev,eqdbData):
              print("Equipment_development_database_is_out_of_synce_with_the_live_version._Please_update_the_development_
     if not checkTimeStamp(labdbDev,labdbData):
              print ("Repository_development_database_is_out_of_synce_with_the_live_version._Please_update_the_development
     print("Exiting...")
     exit()
'add a new version of an existing lab',',
args.add:
     print("Adding_new_lab_version.")
     lab = getLabObject(labdb)
     versionInfo = getVersionInfo(lab, validCourses, validSemesters, semesterKeys, eqdb, disciplineSource, topicSource, softwar
     confirmEntry (versionInfo)
     if validDB(versionInfo, lab, labdb) and validDir(versionInfo, root):
              labdb.save(destXML, ignore_validation=validate, error_log=True)
              if not testMode:
                      moveVersionDir(versionInfo, root)
                      addSupportFolder(versionInfo, root)
     else:
              print("something_when_wrong")
              exit()
'add a new lab',',
args.new:
     print("Adding_new_lab.")
     lab = labdb.newLab(labdb.new_id)
     newLabInfo \, = \, getNewLabInfo \, (\, lab \, , testMode \, )
     lab.name = newLabInfo["name"]
     lab.type = newLabInfo["type"]
     confirmEntry (newLabInfo)
     if validDB(newLabInfo, lab, labdb):
              if not testMode:
                      os.system("mkdir_" + newLabInfo["labFolderPath"])
                      moveVersionDir (newLabInfo, root)
                      add Support Folder (\,new Lab Info\,, root\,)
                      labdb.addLab(lab)
                      labdb.save(destXML, ignore_validation=validate, error_log=True)
              else:
                      os.system("echo_mkdir_" + newLabInfo["labFolder"])
                      labdb.addLab(lab)
                      labdb.save(destXML, ignore_validation=validate, error_log=True)
args.edit:
     print("Editing_existing_lab.")
     lab = getLabObject(labdb)
     lab = getEditInfo(lab, eqdb, disciplineSource, topicSource, softwareSource, testMode)
     if displayLabItem(lab):
             labdb.save(destXML, ignore_validation=validate, error_log=True)
'confirms that the script has ended properly''
nt("...and_then_there_will_be_cake")
```

/usr/bin/python3

```
Script is to be run on web server to update contents of lab repository used in the live version
Written by Peter Gimby, Nov 17 2017
port os, subprocess, argparse, filecmp, time
rtTime = time.process_time()
'define folder locations','
ot = "/usr/local/master/
oSource = root + "pjl-web"
Source = root + "labs"
DDest = "/mnt/local/pjl-web"
DDest = "/mnt/local/labs"
DMount = "/mnt/pjl-web-mnt"
Mount = "/mnt/lab-mnt"
EquipXML = webSource + "/dev/equipmentDB.xml"
aEquipXML = webSource + "/data/equipmentDB.xml"
eEquipXML = webMount + "/data/equipmentDB.xml"
Folders = ["downloads", "equipimg", "equipman", "landingpage", "repository", "safety", "schedules", "web-security"] bFolders = ["css", "data", "dev", "doc", "fonts", "img", "js", "php", "repository", "staffresources"]
bFiles = ["index.html", "README.md"]
bFileReverse = ["equipmentDB.xml"]
untInfo = [{"source": webSource, "mountPt": webMount}, {"source": labSource, "mountPt": labMount}]
'define owners of files and general permissions'''
ner = "pgimby"
up = "pjl_admins"
acheUser = "www-data"
host=["slug","fry"]
bserver="watt.pjl.ucalgary.ca"
f testHost(host):
thishost = os.uname()[1]
 if thishost not in host:
      print ("This_script_is_designed_to_be_run_on_" + thishost + "_only._Exiting...")
      gracefullExit (mountInfo)
f mountFolder(source, mountPoint, remote, option):
fullSource = remote + ":" + source
 os.system("mount_-t_nfs_-o_" + option + "_" + fullSource + "_" + mountPoint)
 if not os.system("mount_|_grep_" + fullSource + "->-/dev/null") == 0:
     print(fullSource + "_did_not_mount_properly._Exiting...")
      gracefullExit (mountInfo)
f umountFolder(mountPoint):
os.system("umount_" + mountPoint )
f \ syncFolder(testMode, source, dest):
print("syning_" + source)
 os.system("rsync" + testMode + "_" + source + "_" + dest)
f getDbFiles(dest, key):
 allFiles = os.listdir(dest)
 dbFiles = []
 for f in allFiles:
      if f.startswith(key) and f.split(".")[0][-1] in ['0', '1', '2', '3', '4', '5', '6', '7']:
          dbFiles.append(f)
 return sorted (dbFiles)
{\bf f\ incrementFiles\,(\,files\,\,,dest\,\,,key\,,source\,\,,osTest\,):}
 for i,f in enumerate(files):
     name = f.split(".")[0]
```

index = int(name[-1])

```
index += 1
      f = name[:-1] + str(index) + ".xml"
 os.system(osTest + "mv_" + dest + "/" + files[i] + "_" + dest + "/" + f)
os.system(osTest + "mv_" + dest + "/" + key + ".xml_" + dest + "/" + key + "-0.xml")
 os.system(osTest + "cp_" + source + "/" + key + ".xml_" + dest + "/" + key + ".xml")
f wheel (dest, key, source, osTest):
 print("updating_equipmentDB.xml")
 dbFiles = getDbFiles(dest, key)
 incrementFiles(list(reversed(dbFiles)), dest, key, source, osTest)
def wheel(dbFile, source, dest, key, osTest):
    print("updating equipmentDB.xml")
    dbFiles = getDbFiles(dest, key)
    #incrementFiles(list(reversed(dbFiles)), dest, key, source, osTest)
f\ change Perm (var Dir, owner, group, file Perm, options, os Test):
 processStart = time.process_time()
 print("changing_permissions_of_" + varDir + "_with_find" + options + "._This_may_take_a_minute.")
  os.system(osTest + "find\_" + varDir + options + "\_-exec\_chmod\_" + filePerm + "\_{}\_\;") \\ os.system(osTest + "find\_" + varDir + options + "\_-exec\_chovn\_" + owner + "." + group + "\_{}\_\;") 
 print("chargePerm_Time:_" + str(time.process_time() - processStart))
f gracefullExit (mountInfo):
 for i in mountInfo:
      umountFolder(i["mountPt"])
 exit()
'checks that file a is newer that file b'''
f whichIsNewer(a,b,testMode):
 if \hspace{0.1cm}os.\hspace{0.1cm}path.\hspace{0.1cm}is\hspace{0.1cm}fil\hspace{0.1cm}e\hspace{0.1cm}(\hspace{0.1cm}a)\hspace{0.1cm} and\hspace{0.1cm}os.\hspace{0.1cm}path.\hspace{0.1cm}is\hspace{0.1cm}fil\hspace{0.1cm}e\hspace{0.1cm}(\hspace{0.1cm}b\hspace{0.1cm})\hspace{0.1cm}\colon\hspace{0.1cm}
      if os.path.getmtime(a) > os.path.getmtime(b):
            if testMode:
                print(a + "_is_newer_than_" + b )
print(a + "_" + str(os.path.getmtime(a)))
print(b + "_" + str(os.path.getmtime(b)))
           return True
      else:
            if testMode:
                 print(b + "_is_newer_than_" + a)
                 print(a + "" + str(os.path.getmtime(a)))
                 print(b + "" + str(os.path.getmtime(b)))
            return False
 else:
      if not os.path.isfile(a):
            print("File_" + a + "_Does_not_exist._Exiting...")
            gracefullExit (mountInfo)
      if not os.path.isfile(b):
    print("File_" + b + "_Does_not_exist._Exiting...")
            gracefullExit (mountInfo)
 \# if os.path.getmtime(a) > os.path.getmtime(b):
 #
        return True
 \# else:
 #
        return False
'Main Script','
'User input to allow for a test mode during development'''
rser = argparse.ArgumentParser()
rser.add_argument('-t', '--test', help='test_adding_to_xml_without_moving_folders', action='store_true')
gs = parser.parse_args()
tMode = args.test
not os.getuid() == 0:
 print("This_script_must_be_run_by_\"The_Great_and_Powerful_Sudo\".")
```

```
'Parameters and options for operating in test mode','
testMode == True:
rsycnOption = "_-avnz_-no-l"
osTest = "echo_"
e :
rsycnOption = "\_-az\_--no-l"
 osTest = ""
'Confirm that this script won't accidently run on the wrong machine'''
tHost (devhost)
'mounts folder for syncing files and confirms success'''
untFolder (webDest, webMount, webserver, "rw")
untFolder(labDest, labMount, webserver, "rw")
'update equipmenDB.xml from web server to development space if it is newer','
which Is Newer (live Equip XML, dev Equip XML, test Mode) \ \ \textbf{and} \ \ which Is Newer (live Equip XML, data Equip XML, test Mode) :
 print("The_live_version_of_equipmentDB.xml_is_newer_than_the_dev_version.")
 if input ("Do_you_wish_to_continue?_y/N_") == "y":
      key = "equipmentDB"
      dataFolder = webSource + "/data"
liveSource = webMount + "/data"
      wheel (dataFolder, key, liveSource, osTest)
      \#wheel(i, source, dest, key, osTest)
      print("Exiting...")
      gracefullExit (mountInfo)
'Set permissions and owners of files and folders''
ngePerm(labSource, owner, group, "644", "_-type_f", osTest)
ngePerm(labSource, owner, group, "755", "_-type_d", osTest)
ngePerm (webSource, owner, group, "644", "L-typeLf", osTest)
. ngePerm (webSource, owner, group, "755", "\_-type\_d", osTest)
'Sets the permission for executable ','
.ngePerm(webSource, owner, group, "750", "\_-type\_f\_-name\_\'*.py\'", osTest)
'rsync lab content folders'',
i in labFolders:
source = labSource + "/" + i + "/"
dest = labMount + "/" + i + "/"
syncFolder(rsycnOption, source, dest)
'rsync webpage folders''
i in webFolders:
source = webSource + "/" + i + "/"
dest = webMount + "/" + i + "/"
syncFolder(rsycnOption, source, dest)
'rsync webpage files','
i in webFiles:
source = webSource + "/" + i
dest = webMount + "/"
syncFolder(rsycnOption, source, dest)
'changes the permissions of specific files and folders needed for live update of equipment numbers'' angePerm(webMount + "/data", "root", "www-data", "660", "_-type_f_-name_equipmentDB.xml", osTest) angePerm(webMount + "/data", "root", "www-data", "775", "_-type_d_-name_\'data\'", osTest)
'unmounts folders used for syncing files'',
ountFolder (webMount)
ountFolder (labMount)
int("Total_Time: " + str(time.process_time() - startTime))
nt("...and_then_there_will_be_cake")
```